Release Notes (93000809)

Digi TransPort LR Product Family

Version 1.2.1.4 – November, 2016

INTRODUCTION

This is a production firmware release for the Digi Transport LR product family.

SUPPORTED PRODUCTS

Digi TransPort LR54W Digi TransPort LR54

SUPPORTED WEB BROWSERS

The following web browsers are supported with the web interface. The latest version and the previous version of each browser have been tested.

- Google Chrome
- Firefox
- Microsoft Internet Explorer 11
- Microsoft Edge

KNOWN ISSUES

- 1. WPA2-Enterprise and WPA Mixed-mode Enterprise security are currently only supported in a single LAN [TLR-3817].
- 2. The "show ipsec" CLI command does not parse certain advanced ipsec settings properly and may return ERROR instead. This is a cosmetic issue [TLR-4136].
- 3. TransPort LR devices cannot be managed by Digi Remote Manager's Profile Manager if profiles have site-specific settings [TLR-4788].
- 4. When configuring a WAN interface with 'probe-interval' and 'timeout', the 'probe-interval' must be less than the timeout interval, otherwise the default route may disappear [TLR-4888].
- 5. A fully qualified domain name (FQDN) cannot be used for configured a WAN interface "probe-host" [TLR-4908].
- 6. When changing a WAN interface "probe-host", the device needs to be rebooted for the change to take effect [TLR-4907].

HISTORY

1.2.1.4 – November, 2016

ENHANCEMENTS

There are no enhancements in this release.

BUG FIXES

- 1. Verizon disconnect issue (TLR-5030, TLR-5132)
- 2. The "Skip Wizard" button would redirect the user to initial Getting Started Wizard page instead of the Dashboard. (URMA-918)
- 3. Getting Started Wizard would show an invalid firmware image on the firmware update page. (URMA-983)

1.2.0.10 - October, 2016

ENHANCEMENTS

Our development has worked hard to deliver the following new features and enhancements:

- 1. Auto-carrier selection based on SIM for AT&T, Verizon and T-Mobile
- 2. Wi-Fi Alliance certification
- 3. Cellular modem firmware update
- 4. Improved Getting Started Wizard
- 5. Vastly improved web interface

BUG FIXES

4. Various.

1.1.0.6 - July, 2016

Initial production release.

1.0.0.4 - May, 2016

Internal release.